



STATE OF NEW YORK

**DEPARTMENT OF STATE**

ONE COMMERCE PLAZA  
99 WASHINGTON AVENUE  
ALBANY, NY 12231-0001

DAVID A. PATERSON  
GOVERNOR

LORRAINE A. CORTÉS-VÁZQUEZ  
SECRETARY OF STATE

**MEMORANDUM**

**TO:** All Fire and Emergency Services Responders

**FROM:** Ron Dunn

**DATE:** November 6, 2009

**SUBJECT:** Chemical Suicides

The Office of Fire Prevention and Control has recently assisted local authorities in two communities with suicides involving chemicals. This method of suicide, sometimes called detergent suicide, is frequently used in Japan and is being seen more frequently in this country. The process involves mixing common household chemicals to create hydrogen sulfide in a small space. Instructions to do this are readily available on the internet and most encourage anyone planning to use this method to provide appropriate warnings to people who might encounter or respond to their situation about the presence of the deadly gas. One incident in Japan took place in the bathroom of an apartment. Over seventy people in neighboring apartments were sickened by the fumes. In Arizona one individual manufactured hydrogen cyanide instead of hydrogen sulfide. This is the only instance of hydrogen cyanide I've been able to discover and suspect it's rare because the chemicals needed for the reaction are not as readily available as those used to make hydrogen sulfide.

Our concern is that anyone who enters the space without proper protection may quickly become a victim themselves. Both recent incidents in New York involved suicides inside a vehicle. One vehicle had very clear and obvious warning signs taped to the window (as in Fig. 1 and 2), the other had signs that were less noticeable laid on the dashboard. In both instances responders were able to recognize the situation and take appropriate protective actions.

It is anticipated that the number of these incidents will rise as more people become aware of the process. The Office of Fire Prevention and Control has developed guidelines to deal with these incidents that I believe local responders will find useful in the event of a chemical suicide in their community.

The attached information is intended to serve as a model protocol. Local agencies may choose to alter these, or implement different policies, based on local training, resources and policies. The important point is that we should be prepared to respond safely to events of this nature. Please distribute this information to the responders in your community.



Fig. 1




Fig. 2



Fig. 3 (chemical containers and pail used for mixing)

## Responding to Chemical Suicides

Responders should be aware that these situations commonly occur in vehicles, residential bathrooms and other small spaces where a small amount of gas can quickly reach lethal concentrations. Dispatchers and call takers should warn callers not to approach, or enter, vehicles, rooms or apartments where unresponsive people may have attempted chemical suicide.

Careful size up of any situation involving an unresponsive person in an enclosed space is critical for responder safety. Responders should wear SCBA and turn out gear whenever they are dealing with a suspected chemical suicide.

Consider wind speed and direction when determining the need to evacuate nearby structures. In an apartment building consideration should be given to evacuating the entire building.

If there is a possibility that the individual may be sleeping, attempt to wake them with a vehicle public address system, bullhorns or sirens.

If individuals cannot be awakened responders should perform a thorough recon before entering the space to assist the victim.

Individuals who initiate chemical suicide may, or may not, place warning signs on doors or windows to indicate the presence of deadly gas inside the space.

Signs may not be easily detected, or understood, by other people – including responders!

Signs may be hidden or obscured by condensation, frost, snow or vapors produced by the reaction.

Interview anyone who may have approached the scene to learn what they saw or smelled. A “rotten egg” smell would indicate hydrogen sulfide; an almond odor is typical of cyanide compounds.

Look for indications that a chemical reaction has been initiated. Typically you will find containers of household chemicals and pails, buckets, pots or other containers where the chemicals have been mixed. There is a possibility that improvised “containers”, such as a sink or the glove box of an automobile, could be used to mix the chemicals.

If you can clearly see that there are no chemical containers and mixing containers present anywhere in the space it is probably not a chemical suicide.

If chemical containers are present attempt to identify the chemicals from labels on the containers, or a sales receipt. The reaction utilizes an acid, such as muriatic or hydrochloric which is found in many common cleaning compounds and a sulfide that would be present in many fungicides, paints, insecticides and shampoo to produce Hydrogen Sulfide.

The presence of containers of potassium cyanide, or cyanide compounds would indicate a reaction that produces hydrogen cyanide. This is less common than the hydrogen sulfide reaction as the cyanides are not as easily obtained.

Air sampling equipment can be used to determine the presence, or absence of hydrogen sulfide or hydrogen cyanide. A small hole may be punched in a car or home window, or a probe, or colorimetric tube inserted in the gap between a door to the room and the floor. A hydrocyanic acid tube will detect hydrogen cyanide. Hydrogen sulfide is heavier than air (VD = 1.19), but hydrogen cyanide is slightly lighter (VD = 0.94)

If the vapor in the space cannot be identified, or the presence of hydrogen cyanide is confirmed entry should only be made by individuals protected by fully encapsulated chemical protective clothing (level A). Hydrogen cyanide is Immediately Dangerous to Life and Health at concentrations above 50 parts per million.

Both hydrogen sulfide and hydrogen cyanide are flammable. The Lower Explosive Level (LEL) of hydrogen sulfide is 4% (40,000 ppm) and the LEL of hydrogen cyanide is 5.6% (56,000 ppm). There have been no incidents of fire reported with these incidents and it is believed that concentrations do not typically reach the LEL except at close proximity to the mixing container. Responders should eliminate ignition sources when ever possible.

The vapors inside the space should be ventilated to the outside. Ensure that no one will be endangered by the vapors before using natural or forced ventilation to air the space out.

Anyone who has been exposed to the vapors should be decontaminated with soap and water. Clothing should be removed and double bagged. Contaminated clothing and PPE should be laundered before being re-used. The victim should be stripped and decontaminated with soap and water before being transported from the scene. Deceased victims should be covered by a sheet, body bags are not recommended.

Expenses related to the clean up may be reimbursed through the State Super Fund or the Environmental Protection Agency. New York State Environmental Conservation employees can assist with this, contact DEC early in the incident. DEC can hire contractors to carry out the clean up; they can not reimburse local responders for their costs associated with incidents.